

Acti

Username: Admin/admin
Password: 12345/123456
IP address: 192. 168.0.100

Arecont Vision

Arecont does not have a default password , but you can reset it to factory settings.
Follow these steps

- 1-Access the camera's web interface by typing the IP in your web browser.
- 2-Under the Administration or System tab, click on Restore to Factory Default.
- 3-Once the camera reboots, all settings on the camera will be restored to factory default

AXIS

For an old system:

Username: Root
Password: Pass
IP Address: 192.168.0.90

But new generation AXIS cameras have a resetting sequence

- 1-Remove the Ethernet cable
- 2-Press and hold the control button and insert the Ethernet cable again while holding the control button.
- 3-Hold the control button until the amber lights turn on.
- 4-Then release the button .
- 5-Wait about 1 minute.
- 6-When the amber lights turns into the green lights your camera is resetted and your password as well

BOSCH

For old models:

Username: service
Password: service
IP Address: 192.168.0.1

For new models:

You can reset the camera by pushing the reset button about 7 seconds. Or you can reset the NVR by removing the battery on the mainboard (not recommended, at your own risk)

DAHUA

Username: admin
Password: admin

GEOVISION

Username: admin
Password: admin
IP Address: 192.168.1.108

HIKVISION

For old models (before firmware 5.3.0)

Username: admin
Password: 12345
IP Address: 192.0.0.64

For new models you can reset password via SADP tool. Please click the link below and follow the instructions on the pdf file

[Hikvision password resetting guide](#)

LTS Security

Username: admin
Password: 12345 or 123456
IP Address: 192.0.0.64

For platinum models please click the link below for pdf file.

[LTS platinum series password reset](#)

Messoa

Username: admin
Password: 1234 or model number of camera
IP address: 192.168.1.30

[Mobotix:](#)

Username: admin

Password: meinsm

[SAMSUNG Techwin](#)

For old models

Username: admin

Password: 111111 or 1111111

For new models

Username: admin

Password: 4321

IP Address: 192.168.1.200

[SONY](#)

Username: admin

Password: admin

IP Address: 192.168.0.100

[Speco](#)

For old models:

Username: root or admin

Password: root or admin

For new models:

Username: admin

Password: 1234

IP Address: 192.168.1.7

[Ubiquiti](#)

Username: ubnt

Password: ubnt

IP Address: 192.168.1.20

[Videocomm](#)

Username: admin

Password: 12345

[Vivotek](#)

None . You can choose your own password after setup. If you want to reset it

1-Press and hold down the reset button for at least 1 minute

2-Power on the camera until the red light flashes rapidly

Now your camera is back to factory default without any password.

For other brands usernames and passwords please see below

Camera Manufacturer	Username	Password	Default IP
3xLogic	admin	12345	192.0.0.64
ACTi	Admin or admin	123456	192.168.0.100
American Dynmics	admin	admin	192.168.1.168
Arecont Vision	admin	no set password	no

			default/DHCP
Avigilon	admin	admin	no default/DHCP
Axis	root	pass or no set password	192.168.0.90
Basler	admin	admin	192.168.100.x
Bosch	service	service	192.168.0.1
Bosch	Dinion	no set password	192.168.0.1
Brickcom	admin	admin	192.168.1.1
Canon	root	Model# of camera	192.168.100.1
CBC Ganz	admin	admin	192.168.100.x
Cisco	no default	no set password	192.168.0.100
CNB	root	admin	192.168.123.1 00
Costar	root	root	unknown
Dahua	admin	admin	192.168.1.108
Digital Watchdog	admin	admin	192.168.1.123
DRS	admin	1234	192.168.0.200
DVTeI	Admin	1234	192.168.0.250
DynaColor	Admin	1234	192.168.0.250

FLIR	admin	fliradmin	192.168.250.16
Foscam	admin	[leave blank]	unknown
GeoVision	admin	admin	192.168.0.10
Grandstream	admin	admin	192.168.1.168
GVI	Admin	1234	192.168.0.250
HIKVision	admin	12345	192.0.0.64
Honeywell	administrator	1234	no default/DHCP
IOImage	admin	admin	192.168.123.10
IPX-DDK	root	Admin or admin	192.168.1.168
IQInvision	root	system	no default/DHCP
JVC	admin	Model# of camera	no default/DHCP
LTS Security	admin	123456	192.0.0.64
March Networks	admin	[leave blank]	unknown
Merit Lilin Camera	admin	pass	no default/DHCP
Merit Lilin Recorder	admin	1111	no default/DHCP

Messoa	admin	Model# of camera	192.168.1.30
Mobotix	admin	meinsm	no default/DHCP
Northern	admin	12345	192.168.1.64
Panasonic	admin	12345	192.168.0.253
Panasonic	admin1	password	192.168.0.253
Pelco	admin	admin	no default/DHCP
PIXORD	admin	admin	192.168.0.200
PIXORD	root	pass	192.168.0.200
QVIS	Admin	1234	192.168.0.250
Samsung	root	4321 or admin	192.168.1.200
Samsung	admin	4321 or 1111111	192.168.1.200
Sanyo	admin	admin	192.168.0.2
Sentry360	Admin	1234	192.168.0.250
Sony	admin	admin	192.168.0.100
Speco	root	root	192.168.1.7
Speco	admin	admin	192.168.1.7
StarDot	admin	admin	no default/DHCP

Starvedia	admin	no set password	no default/DHCP
Toshiba	root	ikwb	192.168.0.30
Trendnet	admin	admin	192.168.10.1
TrueVision	admin	1234	
UDP	root	unknown	unknown
Ubiquiti	ubnt	ubnt	192.168.1.20
W-Box	admin	wbox123	192.0.0.64
Wodsee	admin	[leave blank]	unknown
Verint	admin	admin	no default/DHCP
VideolQ	supervisor	supervisor	no default/DHCP
Vivotek	root	no set password	no default/DHCP